

Configuring Netscape Communicator to Receive InterMail

Select the version of Netscape you are using for configuration instructions.

Netscape Navigator v3.0x

This section describes how to configure Netscape Navigator to access your POP e-mail box.

1. From Options menu, select Mail and News Preferences.
2. Click the **Servers** tab at the top of the dialog box.
 - **Outgoing Mail Server:** 'smtp.registeredsite.com' ****Notice on ISP BLOCKING:** Consult your ISP's documentation if you wish to use your ISP's outgoing mail server.
 - **Incoming Mail Server:** 'pop.registeredsite.com'
 - **POP3 User Name:** popID/yourdomain.com
3. Click the **Identity** tab.
 - **Name:** your name
 - **Your E-mail:** the e-mail address for the POP mailbox
 - **Reply-to Address:** your e-mail address

All other settings are optional. Choosing **Netscape Mail** from the **Window** menu will then open a box that will allow you read and send mail.

Netscape Communicator v4.0x

This section describes how to configure Netscape Communicator to access your POP e-mail box.

1. From the **Edit** menu, select **Preferences**.
2. Open the **Mail & Groups** section, and Click **Mail Server**.
 - **Mail Server User Name:** popID/yourdomain.com
 - **Outgoing Mail Server:** 'smtp.registeredsite.com' ****Notice on ISP BLOCKING:** Consult your ISP's documentation if you wish to use your ISP's outgoing mail server. Also see our article on [ISP blocking](#)..**
 - **Incoming Mail Server:** 'pop.registeredsite.com'
3. Click **Identity** in the left column.
 - **Your Name:** your name

- **E-mail Address:** the e-mail address for the POP mailbox
- **Reply-to Address:** your e-mail address

All the other settings are optional. Choosing **Messenger Mailbox** from the **Communicator** menu will open the part of Netscape that allows you to read and send mail.

Netscape Communicator v4.5x

This section describes how to configure Netscape Communicator to access your POP e-mail box.

1. From the **Edit** menu, select **Preferences**.
2. Open the **Mail & Newsgroups** section and click **Mail Servers**.
 - **Outgoing Mail Server:** 'smtp.registeredsite.com' ****Notice on ISP BLOCKING:** Consult your ISP's documentation if you wish to use your ISP's outgoing mail server. Also see our article on [ISP blocking](#).**
 - Click **Add** to add a new POP Server
3. Configure Pop Server
 - **Server Name:** 'pop.registeredsite.com'
 - **Server Type:** select **POP3 Server**.
 - **User Name:** popID/yourdomain.com
4. Click **Identity** in left column.
 - **Your Name:** your name
 - **E-mail Address:** the e-mail address for the POP mailbox
 - **Reply-to Address:** your e-mail address

All other settings are optional. Choosing **Messenger Mailbox** from the **Communicator** menu will open the part of Netscape that allows you to read and send mail.

Unfortunately, Netscape Messenger does not natively support retrieval of multiple e-mail accounts for POP3 mail servers. To retrieve mail from multiple accounts, you will need to setup additional user profiles using the User Profile Manager supplied with Netscape. See your Netscape documentation for more information.

There are many more options available in Netscape Messenger. See the software's documentation for more information about advanced options.